

PANTONE Color library file for Aldus applications

Note *For the latest information on color libraries, call Tektronix Customer Support in the U.S. and Canada at **1-800-835-6100**. Outside the U.S. and Canada, contact your local Tektronix reseller.*

FreeHand 3.0 and 3.1

The *TEK_540.CLB* file is located in the *APPLSPEC* directory on the Tektronix Windows 3.1 Driver and Printer Utilities diskette. This file is used by the Aldus FreeHand application to properly specify PANTONE Colors for the Phaser 540 printer. This file is application-specific and printer-specific.

1. Copy the *TEK_540.CLB* file to your computer's hard disk; for example, to the FreeHand application directory.
2. Open FreeHand.
3. Use one of the following methods to display the available color libraries:
 - **FreeHand 3.0**
Choose **Library** from the **Colors** palette submenu; a dialog box appears listing available color libraries.
 - **FreeHand 3.1**
Choose **Import** from the **Colors** palette submenu; a dialog box appears listing available color libraries.
4. Select and open the *TEK_540.CLB* color library; a dialog box appears with a list of available colors.
5. Select the colors you want to use, then click **OK**. Selected colors are added to the **Colors** palette, the **Colors** dialog box, and all **Colors** menus.

PageMaker 5.0

The *TEK_540.ACF* file is located in the *APPLSPEC* directory on the Tektronix Windows 3.1 Driver and Printer Utilities diskette. This file is used by the application to properly specify PANTONE Colors for Aldus PageMaker and a Phaser 540 printer. This file is application-specific and printer-specific.

1. Copy the *TEK_540.ACF* file from the Tektronix Windows 3.1 Driver and Printer Utilities diskette to your hard disk.
2. Place the file in the *USENGLSH\COLOR* subdirectory in the *ALDUS* application directory.
3. Start PageMaker.
4. Choose **Element, Define Colors, New, Libraries**, then select the Phaser 540.